

# Standard Letter Document Class for L<sup>A</sup>T<sub>E</sub>X version 2e

Leslie Lamport and Frank Mittelbach and Rainer Schöpf

July 1, 1998

## Contents

<b>1 Initial Code</b>	<b>2</b>
1.1 Setting Paper Sizes . . . . .	2
1.2 Choosing the type size . . . . .	3
1.3 Two-side or one-side printing . . . . .	3
1.4 Draft option . . . . .	3
1.5 Equation numbering on the left . . . . .	4
1.6 Flush left displays . . . . .	4
<b>2 Executing Options</b>	<b>4</b>
<b>3 Loading Packages</b>	<b>4</b>
<b>4 Document Layout</b>	<b>4</b>
4.1 Paragraphing . . . . .	4
4.2 Page Layout . . . . .	5
4.2.1 Vertical spacing . . . . .	5
4.2.2 The dimension of text . . . . .	6
4.2.3 Margins . . . . .	6
4.2.4 Footnotes . . . . .	7
4.3 Page Styles . . . . .	7
4.3.1 Marking conventions . . . . .	7
4.3.2 Defining the page styles . . . . .	8
<b>5 Document Markup</b>	<b>9</b>
5.1 Global Declarations . . . . .	9
5.2 The generic letter commands . . . . .	10
5.2.1 Page breaking control . . . . .	11
5.3 Customizing the labels . . . . .	14
5.4 Lists . . . . .	15
5.4.1 General List Parameters . . . . .	15
5.4.2 Enumerate . . . . .	17

5.4.3	Itemize	17
5.4.4	Description	17
5.5	Defining new environments	18
5.5.1	Verse	18
5.5.2	Quotation	18
5.5.3	Quote	18
5.5.4	Theorem	18
5.6	Setting parameters for existing environments	19
5.6.1	Array and tabular	19
5.6.2	Tabbing	19
5.6.3	Minipage	19
5.6.4	Framed boxes	19
5.6.5	Equation and eqnarray	20
5.7	Font changing	20
5.8	Footnotes	21
5.9	Words	22
5.10	Date	22
5.11	Two column mode	22
5.12	The page style	22
5.13	Single or double sided printing	22

## 1 Initial Code

In this part we define a few commands that are used later on.

`\@ptsize` This control sequence is used to store the second digit of the pointsize we are typesetting in. So, normally, its value is one of 0, 1 or 2.

```
1 (*letter)
2 \newcommand{\@ptsize{}}
```

### 1.1 Setting Paper Sizes

The variables `\paperwidth` and `\paperheight` should reflect the physical paper size after trimming. For desk printer output this is usually the real paper size since there is no post-processing.

```
3 \DeclareOption{a4paper}
4   {\setlength{\paperheight}{297mm}%
5    \setlength{\paperwidth}{210mm}}
6 \DeclareOption{a5paper}
7   {\setlength{\paperheight}{210mm}%
8    \setlength{\paperwidth}{148mm}}
9 \DeclareOption{b5paper}
10  {\setlength{\paperheight}{250mm}%
11   \setlength{\paperwidth}{176mm}}
12 \DeclareOption{letterpaper}
13  {\setlength{\paperheight}{11in}}%
```

```

14   \setlength\paperwidth {8.5in}
15 \DeclareOption{legalpaper}
16   {\setlength\paperheight {14in}%
17   \setlength\paperwidth {8.5in}}
18 \DeclareOption{executivepaper}
19   {\setlength\paperheight {10.5in}%
20   \setlength\paperwidth {7.25in}}

```

The option `landscape` switches the values of `\paperheight` and `\paperwidth`, assuming the dimensions were given for portrait paper.

```

21 \DeclareOption{landscape}
22   {\setlength\@tempdima {\paperheight}%
23   \setlength\paperheight {\paperwidth}%
24   \setlength\paperwidth {\@tempdima}}

```

## 1.2 Choosing the type size

The type size options are handled by defining `\@ptsize` to contain the last digit of the size in question and branching on `\ifcase` statements. This is done for historical reasons to stay compatible with other packages that use the `\@ptsize` variable to select special actions. It makes the declarations of size options less than 10pt difficult, although one can probably use 9 and 8 assuming that a class wont define both 8pt and 18pt options.

```

25 \DeclareOption{10pt}{\renewcommand{\@ptsize{0}}}
26 \DeclareOption{11pt}{\renewcommand{\@ptsize{1}}}
27 \DeclareOption{12pt}{\renewcommand{\@ptsize{2}}}

```

## 1.3 Two-side or one-side printing

Two-sided printing was not supported in the L<sup>A</sup>T<sub>E</sub>X 2.09 version of this document class.

```

28 \if@compatibility
29   \DeclareOption{twoside}{\@latexerr{No 'twoside' layout for letters}%
30                         \@eha}
31 \else
32   \DeclareOption{twoside}{\@twosidetrue \@mparswitchtrue}
33 \fi
34 \DeclareOption{oneside}{\@twosidefalse \@mparswitchfalse}

```

## 1.4 Draft option

If the user requests `draft` we show any overfull boxes. We could probably add some more interesting stuff to this option.

```

35 \DeclareOption{draft}{\setlength\overfullrule{5pt}}
36 \DeclareOption{final}{\setlength\overfullrule{0pt}}

```

## 1.5 Equation numbering on the left

The option `leqno` can be used to get the equation numbers on the left side of the equation.

37 \DeclareOption{leqno}{\input{leqno.clo}}

## 1.6 Flush left displays

The option `fleqn` redefines the displayed math environments in such a way that they come out flush left, with an indentation of `\mathindent` from the prevailing left margin.

38 \DeclareOption{fleqn}{\input{fleqn.clo}}

# 2 Executing Options

Here we execute the default options to initialize certain variables.

39 \ExecuteOptions{letterpaper,10pt,oneside,onecolumn,final}

The `\ProcessOptions` command causes the execution of the code for every option `foo` which is declared and for which the `foo` option in his `\documentclass` command. For every option `bar` he typed, which is not declared, the option is assumed to be a global option. All options will be passed as document options to any `\usepackage` command in the document preamble.

40 \ProcessOptions

Now that all the options have been executed we can load the chosen class option file that contains all size dependant code.

41 \input{size1@ptsize.clo}

# 3 Loading Packages

The standard class files do not load additional packages.

# 4 Document Layout

In this section we are finally dealing with the nasty typographical details.

## 4.1 Paragraphing

`\lineskip` These parameters control T<sub>E</sub>X's behavior when two lines tend to come too close together.  
`\normallineskip`

42 \setlength{\lineskip}{1pt}

43 \setlength{\normallineskip}{1pt}

<code>\baselinestretch</code>	This is used as a multiplier for <code>\baselineskip</code> . The default is to <i>not</i> stretch the baselines.
	44 <code>\renewcommand\baselinestretch{}</code>
<code>\parskip</code>	<code>\parskip</code> gives extra vertical space between paragraphs and <code>\parindent</code> is the width of the paragraph indentation. Letters are typeset without paragraph indentation.
<code>\parindent</code>	45 <code>\setlength\parskip{0.7em}</code> 46 <code>\setlength\parindent{0\p@}</code>
<code>\@lowpenalty</code>	The commands <code>\nopagebreak</code> and <code>\nolinebreak</code> put in penalties to discourage
<code>\@medpenalty</code>	these breaks at the point they are put in. They use <code>\@lowpenalty</code> , <code>\@medpenalty</code>
<code>\@highpenalty</code>	or <code>\@highpenalty</code> , dependant on their argument.
	47 <code>\@lowpenalty 51</code> 48 <code>\@medpenalty 151</code> 49 <code>\@highpenalty 301</code>
<code>\clubpenalty</code>	These penalties are used to discourage club and widow lines. Because we use their
<code>\widowpenalty</code>	default values we only show them here, commented out.
	50 % <code>\clubpenalty 150</code> 51 % <code>\widowpenalty 150</code>
<code>\displaywidowpenalty</code>	Discourage (but not so much) widows in front of a math display and forbid breaking directly in front of a display. Allow break after a display without a penalty.
<code>\predisplaypenalty</code>	Again the default values are used, therefore we only show them here.
<code>\postdisplaypenalty</code>	52 % <code>\displaywidowpenalty 50</code> 53 % <code>\predisplaypenalty 10000</code> 54 % <code>\postdisplaypenalty 0</code>
<code>\interlinepenalty</code>	Allow the breaking of a page in the middle of a paragraph.
	55 % <code>\interlinepenalty 0</code>
<code>\brokenpenalty</code>	We allow the breaking of a page after a hyphenated line.
	56 % <code>\brokenpenalty 0</code>

## 4.2 Page Layout

All margin dimensions are measured from a point one inch from the top and lefthand side of the page.

### 4.2.1 Vertical spacing

<code>\headheight</code>	The <code>\headheight</code> is the height of the box that will contain the running head. The
<code>\headsep</code>	<code>\headsep</code> is the distance between the bottom of the running head and the top of
	the text. <code>\topskip</code> is the <code>\baselineskip</code> for the first line on a page, its value
	depends on the size option that was specified. Therefore it is initialized in one of
	the <code>size1x.clo</code> files.
	57 <code>\setlength\headheight{12\p@}</code> 58 <code>\setlength\headsep {45\p@}</code>

`\footskip` The distance from the baseline of the box which contains the running footer to the baseline of last line of text is controlled by the `\footskip`. Bottom of page:  
 59 `\setlength\footskip{25\p@}`

#### 4.2.2 The dimension of text

`\textwidth` When we are in compatibility mode we have to make sure that the dimensions of the printed area are not different from what the user was used to see.

```
60 \if@compatibility
61   \setlength\textwidth{365\p@}
```

`\textheight` Now that we have computed the width of the text, we have to take care of the height. The `\textheight` is the height of text (including footnotes and figures, excluding running head and foot).

```
62   \setlength\textheight{505\p@}
63 \fi
```

In native mode we use the dimensions as they were computed by one of the `xxpt` options, together with one of the `..paper` options.

#### 4.2.3 Margins

`\oddsidemargin` The values of `\oddsidemargin` and `\evensidemargin` are computed from those of `\paperwidth` and `\textwidth`.

`\marginparwidth`

```
64 \if@compatibility
65   \setlength\oddsidemargin{53pt}
66   \setlength\evensidemargin{53pt}
67   \setlength\marginparwidth{90pt}
68 \else
69   \setlength\@tempdima{\paperwidth}
70   \addtolength\@tempdima{-2in}
71   \addtolength\@tempdima{-\textwidth}
72   \setlength\oddsidemargin  {.5\@tempdima}
73   \setlength\evensidemargin {\oddsidemargin}
74   \setlength\marginparwidth {90\p@}
75 \fi
```

`\marginparsep` The horizontal space between the main text and marginal notes is determined by `\marginparsep`, the minimum vertical separation between two marginal notes is controlled by `\marginparpush`.

```
76 \setlength\marginparsep {11\p@}
77 \setlength\marginparpush{5\p@}
```

`\topmargin` The `\topmargin` is the distance between the top of ‘the printable area’ –which is 1 inch below the top of the paper– and the top of the box which contains the running head.

It can now be computed from the values set above.

```
78 \setlength\topmargin{27pt}
```

#### 4.2.4 Footnotes

\footnotesep	\footnotesep is the height of the strut placed at the beginning of every footnote. It equals the height of a normal \footnotesize strut in this class, thus no extra space occurs between footnotes.
	79 \setlength{\footnotesep}{12\p0}
\footins	\skip\footins is the space between the last line of the main text and the top of the first footnote.
	80 \setlength{\skip\footins}{10\p0 \oplus 2\p0 \ominus 4\p0}

### 4.3 Page Styles

The page style *foo* is defined by defining the command \ps@*foo*. This command should make only local definitions. There should be no stray spaces in the definition, since they could lead to mysterious extra spaces in the output (well, that's something that should be always avoided).

\@evenhead \@oddhead \@evenfoot \@oddfoot	The \ps@... command defines the macros \@oddhead, \@oddfoot, \@evenhead, and \@evenfoot to define the running heads and feet—e.g., \@oddhead is the macro to produce the contents of the heading box for odd-numbered pages. It is called inside an \hbox of width \textwidth.
--	--

#### 4.3.1 Marking conventions

To make headings determined by the sectioning commands, the page style defines the commands \chaptermark, \sectionmark, ..., where \chaptermark{<text>} is called by \chapter to set a mark, and so on.

The \...mark commands and the \...head macros are defined with the help of the following macros. (All the \...mark commands should be initialized to no-ops.)

L<sup>A</sup>T<sub>E</sub>X extends T<sub>E</sub>X's \mark facility by producing two kinds of marks, a 'left' and a 'right' mark, using the following commands:

\markboth{<left>}{<right>}: Adds both marks.
\markright{<right>}: Adds a 'right' mark.
\leftmark: Used in the \@oddhead, \@oddfoot, \@evenhead or \@evenfoot macros, it gets the current 'left' mark. \leftmark works like T <sub>E</sub> X's \botmark command.
\rightmark: Used in the \@oddhead, \@oddfoot, \@evenhead or \@evenfoot macros, it gets the current 'right' mark. \rightmark works like T <sub>E</sub> X's \firstmark command.

The marking commands work reasonably well for right marks 'numbered within' left marks—e.g., the left mark is changed by a \chapter command and the right mark is changed by a \section command. However, it does produce somewhat anomalous results if two \markboth's occur on the same page.

Commands like `\tableofcontents` that should set the marks in some page styles use a `\@mkboth` command, which is `\let` by the pagestyle command (`\ps@...`) to `\markboth` for setting the heading or to `\@gobbletwo` to do nothing.

### 4.3.2 Defining the page styles

The pagestyles `empty` and `plain` are defined in the L<sup>A</sup>T<sub>E</sub>X kernel (`ltpage.dtx`), but these definitions are changed to a simpler version for this document class.

- `\ps@headings` The definition of the page style `headings` has to be different for two sided printing than it is for one sided printing.

```
81 \if@twoside
82   \def\ps@headings{%
```

The running feet are empty in this page style.

```
83     \let\@oddfoot\@empty\let\@evenfoot\@empty
```

The running head contains some information about this letter. The head is the same for even and odd pages.

```
84     \def\@oddhead{\slshape\headtoname{} \ignorespaces\tename
85           \hfil \cdate
86           \hfil \pagename{} \thepage}%
87     \let\@evenhead\@oddhead}
```

For one sided printing we don't need to define `\@evenhead` so the definition is somewhat simpler.

```
88 \else
89   \def\ps@headings{%
90     \let\@oddfoot\@empty
91     \def\@oddhead{\slshape\headtoname{} \ignorespaces\tename
92           \hfil \cdate
93           \hfil \pagename{} \thepage}%
94 \fi
```

- `\ps@empty` The definition of the page style `empty` is simple: No running head or foot at all.

```
95 \def\ps@empty{%
96   \let\@oddfoot\@empty\let\@oddhead\@empty
97   \let\@evenfoot\@empty\let\@evenhead\@empty}
```

- `\ps@firstpage` The page style `firstpage` puts the telephone number in the proper place for the letterhead. It should be adapted to site conventions. The size of the number is determined depending on the main size.

```
98 \def\ps@firstpage{%
99   \let\@oddhead\@empty
100  \def\@oddfoot{\raisebox{-45\p@}{[\z@}}{%
101    \hb@xt@\textwidth{\hspace*{100\p@}}%
102    \ifcase \@ptsize \relax
103      \normalsize
104    \or
```

```

105          \small
106          \or
107          \footnotesize
108          \fi
109      \fromlocation \hfill \telephonenum}\}\hss}}

```

\ps@plain The definition of the page style *plain* is again simple.

```

110 \def\ps@plain{%
111     \let\@oddhead\empty
112     \def\@oddfoot{\normalfont\hfil\thepage\hfil}%
113     \def\@evenfoot{\normalfont\hfil\thepage\hfil}%
}

```

## 5 Document Markup

### 5.1 Global Declarations

\name The following declarations, shown with examples, give information about the sender:

```

\address • \name{Dr. L. User} : to be used for the return address on the envelope.
\location • \signature{Larry User} : goes after the closing.
\telephone 114   \newcommand*\name[1]{\def\fromname{#1}}
                  • \signature{Larry User} : goes after the closing.
115   \newcommand*\signature[1]{\def\fromsig{#1}}
                  • \address{3245 Foo St.\Gnu York} : used as the return address in the
                  letter and on the envelope. If not declared, then an institutional standard
                  address is used.
116   \newcommand*\address[1]{\def\fromaddress{#1}}
                  • \location{Room 374} : Acts as modifier to the standard institutional ad-
                  dress.
117   \newcommand*\location[1]{\def\fromlocation{#1}}
                  • \telephone{(415)123-4567} : Just in case some style puts it on the letter.

```

```
118   \newcommand*\telephone[1]{\def\telephonenum{#1}}
```

\fromname We make sure that the internal control sequences that are used to store the information exist and are empty.

```

\fromsig 119 \name{}
\fromaddress 120 \signature{}
\fromlocation 121 \address{}
\telephonenum 122 \location{}
123 \telephone{}

```

\makelabels The \makelabels declaration causes mailing labels to be made.

```
124 \newcommand*\makelabels{%
  At the beginning of the document, we need to activate the \cmlabel and
  \startlabels commands, as well as write \startlabels to the .aux file.
125   \AtBeginDocument{%
126     \let\startlabels\startlabels
127     \let\cmlabel\mlabel
128     \if@filesw
129       \immediate\write\mainaux{\string\startlabels\fi}%

```

At the end of the document we need to write \clearpage to the .aux file.

```
130   \AtEndDocument{%
131     \if@filesw\immediate\write\mainaux{\string\clearpage\fi}%

```

\makelabels is allowed only before the \begin{document} command.

```
132 \onlypreamble\makelabels
```

## 5.2 The generic letter commands

**letter** The letter environment creates a new letter, starting from page 1. (The first page is unnumbered.) It has a single argument, which is the addressee and his address, as in

```
\begin{letter}{Sam Jones \\
  Institute for Retarded Study\\
  Princeton, N.J.}
```

Local declarations, such as \address, can follow the \begin{letter}.

```
133 \newenvironment{letter}[1]
134   {\newpage
135   \if@twoside \ifodd\c@page
136     \else\thispagestyle{empty}\null\newpage\fi
137   \fi
138   \c@page\@ne
139   \interlinepenalty=200 % smaller than the TeXbook value
```

The \leavevmode and \ignorespaces commands are there for protecting against an empty argument.

```
140   \process{\\leavevmode\\ignorespaces #1}}
```

The end of the environment possibly writes the address information on the .aux file.

```
141   {\stopletter\\par\\pagebreak\\par
142   \if@filesw
143     \begingroup
144       \let\\=\relax
145       \let\protect\\unexpandable\protect
146       \immediate\write\auxout{%
147         \string\cmlabel{\returnaddress}{\toname\\\toaddress}}%
148     \endgroup
149   \fi}
```

```

\@processto \@processto gets the \toname and \toaddress from the letter environment's
  \@xproc macro argument. \@xproc and \@yproc are auxiliary macros.
\@yproc 150 \long\def\@processto#1{%
  151   \@xproc #1\\@@@%
  152   \ifx\toaddress\@empty
  153   \else
  154     \@yproc #1@@@%
  155   \fi}
  156 \long\def\@xproc #1\\#2@@@\{\def\toname{#1}\def\toaddress{#2}\}
  157 \long\def\@yproc #1\\#2@@@\{\def\toaddress{#2}\}

```

### 5.2.1 Page breaking control

\stopbreaks When the command \stopbreaks is issued no page breaks should occur until \startbreaks is called.

```

158 \newcommand*\stopbreaks{%
  159   \interlinepenalty\@M
  160   \def\par{\@par\nobreak}%
  161   \let\\@nobreakcr
  162   \let\vspace\@nobreakvspace}

\nobreakvspace These are needed by \stopbreaks
\nobreakvspace 163 \DeclareRobustCommand\@nobreakvspace
\nobreakcr 164   {\@ifstar{\nobreakvspace}{\nobreakvspace}}
  165 \def\@nobreakvspace#1{%
  166   \ifvmode
  167     \nobreak\vskip #1\relax
  168   \else
  169     \obphack\vadjust{\nobreak\vskip #1}\esphack
  170   \fi}
  171 \def\@nobreakcr{\@ifstar{\@normalcr}{\@normalcr*}}
```

\startbreaks This cancels the effect of \stopbreaks.

```

172 \newcommand*\startbreaks{%
  173   \let\\@normalcr
  174   \interlinepenalty 200%
  175   \def\par{\@par\penalty 200\relax}}
```

\longindentation The size of the indent to use before the closing of the letter.

```

176 \newdimen\longindentation
177 \longindentation=.5\textwidth
```

\indentedwidth The width of the closing of the letter.

```

178 \newdimen\indentedwidth
179 \indentedwidth=\textwidth
180 \advance\indentedwidth -\longindentation
```

\opening Text is begun with the \opening command, whose argument generates the salutation, as in

```
\opening{Dear Henry,}
```

This should produce everything up to and including the ‘Dear Henry,’ and a \par command that follows. Since there’s a \vfil at the bottom of every page, it can add vertical fill to position a short letter. It should use the following commands:

- \toname : name part of ‘to’ address. Will be one line long.
- \toaddress : address part of ‘to’ address. The lines separated by \\.
- \fromname : name of sender.
- \fromaddress : argument of current \address declaration– null if none. Should use standard institutional address if null.
- \fromlocation : argument of current \location declaration–null if none.
- \telephonenum : argument of current \telephone declaration–null if none.

```
181 \newcommand*{\opening}[1]{\ifx\@empty\fromaddress
182   \thispagestyle{firstpage}%
183   {\raggedleft\@date\par}%
184 \else % home address
185   \thispagestyle{empty}%
186   {\raggedleft\begin{tabular}{l}\ignorespaces
187     \fromaddress \\*[2\parskip]%
188     \@date \end{tabular}\par}%
189 \fi
190 \vspace{2\parskip}%
191 {\raggedright \toname \\ \toaddress \par}%
192 \vspace{2\parskip}%
193 #1\par\nobreak}
```

\closing The body of the letter follows, ended by a \closing command, as in

```
\closing{Yours truly,}
```

This command generates the closing matter, and the signature. An obvious thing to do is to use a \parbox for the closing and the signature. Should use the following:

- \fromsig : argument of current \signature declaration or, if null, the \fromname.
- \stopbreaks : a macro that inhibits page breaking.

```
194 \newcommand{\closing}[1]{\par\nobreak\vspace{\parskip}%
195   \stopbreaks
196   \noindent
197   \ifx\@empty\fromaddress\else
```

```

198  \hspace*{\longindentation}\fi
199  \parbox{\indentedwidth}{\raggedright
200      \ignorespaces #1\\[6\medskipamount]%
201      \ifx\empty\fromsig
202          \fromname
203      \else \fromsig \fi\strut}%
204  \par}

```

\smallskipamount Of these three, only \medskipamount is actually used above.

```

\medskipamount 205 \%{ \smallskipamount=.5\parskip
\bigskipamount 206 \medskipamount=\parskip
207 \%{ \bigskipamount=2\parskip

```

\cc After the \closing you can put arbitrary stuff, which is typeset with zero  
\encl \parindent and no page breaking. Commands designed for use after the clos-  
\ps ing are:

```
\cc{Tinker\|Evers\|Chance}
```

which produces:

```
cc: Tinker
    Evers
    Chance
```

Note the obvious use of \parbox.

```

208 \newcommand*{\cc}[1]{%
209   \par\noindent
210   \parbox[t]{\textwidth}{%
211     \hangfrom{\normalfont\ccname: }%
212     \ignorespaces #1\strut}\par}
213 \encl{Foo(2)\|Bar}

```

which produces:

```
encl: Foo(2)
      Bar
```

```

213 \newcommand*{\encl}[1]{%
214   \par\noindent
215   \parbox[t]{\textwidth}{%
216     \hangfrom{\normalfont\enclname: }%
217     \ignorespaces #1\strut}\par}

```

The only thing \ps needs to do is call \startbreaks, which allows page break-  
ing again.

```
218 \newcommand*{\ps}{\par\startbreaks}
```

\stopletter The \stopletter command is called by \endletter to do the following:

- Add any desired fill or other material at the end of the letter.

- Define `\returnaddress` to be the return address for the mailing label. More precisely, it is the first argument of the `\mlabel` command described below. It should be defined to null if the return address doesn't appear on the labels. Any command, other than `\backslash`, that should not be expanded until the `\mlabel` command is actually executed must be preceded by `\protect`. Whenever possible, `\protect` commands in the definition of `\returnaddress`—it's much more efficient that way. In particular, when the standard return address is used, you should define `\returnaddress` to something like `\protect\standardreturnaddress`.

219 `\newcommand*{\stopletter}{}{}`

### 5.3 Customizing the labels

Commands for generating the labels are put on the `.aux` file, which is read in and processed by the `\end{document}` command. You have to define the following two commands:

- `\startlabels` : Should reset the page layout parameters if necessary.
- `\mlabel{<return address>}{<to address>}` : Command to generate a single label.

`\returnaddress` The return address for the mailing labels can be stored in this macro.

220 `\newcommand*{\returnaddress}{}{}`

`\labelcount` A register to count the labels

221 `\newcount\labelcount`

`\startlabels` The following `\startlabels` command sets things up for producing labels in two columns of five 2" × 4-1/4" labels each, suitable for reproducing onto Avery brand number 5352 address labels.

```
222 \newcommand*{\startlabels}{\labelcount\z@
223   \pagestyle{empty}%
224   \let\@texttop\relax
225   \topmargin -50\p@
226   \headsep \z@
227   \oddsidemargin -35\p@
228   \evensidemargin -35\p@
229   \textheight 10in
230   \colht\textheight \colroom\textheight \vsize\textheight
231   \textwidth 550\p@
232   \columnsep 26\p@
233   \ifcase \ptsize\relax
234     \normalsize
235   \or
236     \small
237   \or
238     \footnotesize
```

```

239   \fi
240   \baselineskip \z@
241   \lineskip \z@
242   \boxmaxdepth \z@
243   \parindent \z@
244   \twocolumn\relax}

\@startlabels  \@startlabels is the command name that is written to the .aux file. It is a no-op at first, and defined to be the same as \startlabels in the \begin{document} hook.
245 \let\@startlabels=\relax

\mlabel This command prints an address label; it is used when the user specified \makelabels in the preamble of his document. The command \mlabel takes two arguments; the second argument is supposed to be the address; the first argument can be used to print a return address. In this document class we ignore the first argument. Also the labels are supposed to be 2 inch high and 3.6 inch wide. When your address labels have a different you will have to define your own \mlabel command.
246 \newcommand*\mlabel[2]{%
247   \parbox[b][2in][c]{262pt}{\strut\ignorespaces #2}%
248 }

\@mlabel The macro \@mlabel is written to the .aux file instead of \mlabel. This allows us to make it a no-op by default, and then activate it in the \begin{document} hook.
249 \let\@mlabel=\@gobbletwo

```

## 5.4 Lists

### 5.4.1 General List Parameters

The following commands are used to set the default values for the list environment's parameters. See the L<sup>A</sup>T<sub>E</sub>X manual for an explanation of the meanings of the parameters. Defaults for the list environment are set as follows. First, \rightmargin, \listparindent and \itemindent are set to 0pt. Then, for a Kth level list, the command \@listK is called, where 'K' denotes 'i', 'ii', ... , 'vi'. (I.e., \@listiii is called for a third-level list.) By convention, \@listK should set \leftmargin to \leftmarginK.

```

\leftmargin \leftmargini For efficiency, level-one list's values are defined at top level, and \@listi is defined
\leftmargini to set only \leftmargin.
\leftmarginii 250 \setlength{\leftmargini}{2.5em}
\leftmarginiii \leftmarginiv \leftmarginv The following three are calculated so that they are larger than the sum of
\leftmarginvi \leftmarginvii \leftmarginviii \labelsep and the width of the default labels (which are '(m)', 'vii.' and 'M.').
\leftmarginvii 251 \setlength{\leftmarginii}{2.2em}
\leftmarginviii 252 \setlength{\leftmarginiii}{1.87em}

```

```

253 \setlength{\leftmarginiv}{1.7em}
254 \setlength{\leftmarginv}{1em}
255 \setlength{\leftmarginvi}{1em}

    Here we set the top level leftmargin.

256 \setlength{\leftmargin}{\leftmargini}

\labelsep \labelsep is the distance between the text of an item; \labelwidth
\labelwidth is the width of the label.

257 \setlength{\labelsep}{5pt}
258 \setlength{\labelwidth}{\leftmargini}
259 \addtolength{\labelwidth}{-\labelsep}

\partopsep When the user leaves a blank line before the environment an extra vertical space
of \partopsep is inserted, in addition to \parskip and \topsep.

260 \setlength{\partopsep}{0pt}

\@beginparpenalty These penalties are inserted before and after a list or paragraph environment.
\@endparpenalty They are set to a bonus value to encourage page breaking at these points.

\@itempenalty This penalty is inserted between list items.

261 \@beginparpenalty -\@lowpenalty
262 \@endparpenalty -\@lowpenalty
263 \@itempenalty -\@lowpenalty

\@listI \@listI defines top level and \@listi values of \leftmargin, \parsep, \topsep,
\@listi and \itemsep

264 \def\@listI{\setlength{\leftmargin}{\leftmargini}%
265             \setlength{\parsep}{0pt}%
266             \setlength{\topsep}{.4em}%
267             \setlength{\itemsep}{.4em}%
268 \let\@listi\@listI

    We have to initialize these parameters.

269 \@listi

\@listii Here are the same macros for the higher level lists.

\@listiii 270 \def\@listii{\setlength{\leftmargin}{\leftmarginii}%
\@listiv 271             \setlength{\labelwidth}{\leftmarginii}%
\@listv 272             \addtolength{\labelwidth}{-\labelsep}%
\@listvi 273 \def\@listiii{\setlength{\leftmargin}{\leftmarginiii}%
274             \setlength{\labelwidth}{\leftmarginiii}%
275             \addtolength{\labelwidth}{-\labelsep}%
276             \setlength{\topsep}{.2em}%
277             \setlength{\itemsep}{\topsep}%
278 \def\@listiv{\setlength{\leftmargin}{\leftmarginiv}%
279             \setlength{\labelwidth}{\leftmarginiv}%
280             \addtolength{\labelwidth}{-\labelsep}%
281 \def\@listv{\setlength{\leftmargin}{\leftmarginv}}%

```

```

282           \setlength \labelwidth{\leftmargini}%
283           \addtolength\labelwidth{-\labelsep}%
284 \def\@listvi {\setlength \leftmargin{\leftmargini}%
285           \setlength \labelwidth{\leftmargini}%
286           \addtolength\labelwidth{-\labelsep}}%

```

#### 5.4.2 Enumerate

The enumerate environment uses four counters: *enumi*, *enumii*, *enumiii* and *enumiv*, where *enumN* controls the numbering of the Nth level enumeration.

<i>\theenumi</i>	The counters are already defined in the L <sup>A</sup> T <sub>E</sub> X kernel ( <i>ltlists.dtx</i> ), but their representation is changed here.
<i>\theenumii</i>	287 \renewcommand\theenumi{@arabic\c@enumi}
<i>\theenumiv</i>	288 \renewcommand\theenumii{@alph\c@enumii}
	289 \renewcommand\theenumiii{@roman\c@enumiii}
	290 \renewcommand\theenumiv{@Alpha\c@enumiv}
<i>\labelenumi</i>	The commands <i>\labelenumi</i> ... <i>\labelenumiv</i> generate the label for each item.
<i>\labelenumii</i>	291 \newcommand\labelenumi{\theenumi.}
<i>\labelenumiii</i>	292 \newcommand\labelenumii{(\theenumii)}
<i>\labelenumiv</i>	293 \newcommand\labelenumiii{(\theenumiii.)}
	294 \newcommand\labelenumiv{(\theenumiv.)}
<i>\p@enumii</i>	The expansion of <i>\p@enumN\theenumN</i> defines the output of a <i>\ref</i> command
<i>\p@enumiii</i>	when referencing an item of the Nth level of an enumerated list.
<i>\p@enumiv</i>	295 \renewcommand\p@enumii{\theenumi}
	296 \renewcommand\p@enumiii{(\theenumi(\theenumii))}
	297 \renewcommand\p@enumiv{\p@enumii\theenumiii}

#### 5.4.3 Itemize

<i>\labelitemi</i>	Itemization is controlled by <i>\labelitemi</i> , <i>\labelitemii</i> , <i>\labelitemiii</i> , and
<i>\labelitemii</i>	<i>\labelitemiv</i> , which define the labels of the various itemization levels: the symbols used are bullet, bold en-dash, asterisk and centered dot.
<i>\labelitemiii</i>	
<i>\labelitemiv</i>	298 \newcommand\labelitemi{\textbullet}
	299 \newcommand\labelitemii{\normalfont\bfseries \textendash}
	300 \newcommand\labelitemiii{\textasteriskcentered}
	301 \newcommand\labelitemiv{\textperiodcentered}

#### 5.4.4 Description

<i>\description</i>	The description environment is defined here – while the itemize and enumerate environments are defined in the L <sup>A</sup> T <sub>E</sub> X kernel ( <i>ltlists.dtx</i> ).
---------------------	--

302 \newenvironment{description}	
303           {\list{}{\labelwidth\z@\itemindent-\leftmargin}	
304               \let\makelabel\descriptionlabel}}	
305           {\endlist}	

```
\descriptionlabel To change the formatting of the label, you must redefine \descriptionlabel.
```

```
306 \newcommand*\descriptionlabel[1]{\hspace\labelsep  
307 \normalfont\bfseries #1}
```

## 5.5 Defining new environments

### 5.5.1 Verse

**verse** The verse environment is defined by making clever use of the list environment's parameters. The user types \\ to end a line. This is implemented by \let'ing \\ equal \centercr.

```
308 \newenvironment{verse}  
309 { \let\\=\@centercr  
310 \list{}{\setlength\itemsep{\z@}%  
311 \setlength\itemindent{-15\p@}%  
312 \setlength\listparindent{\itemindent}%  
313 \setlength\rightmargin{\leftmargin}%  
314 \addtolength\leftmargin{15\p@}}%  
315 \item[]  
316 \endlist}
```

### 5.5.2 Quotation

**quotation** The quotation environment is also defined by making clever use of the list environment's parameters. The lines in the environment are set smaller than \textwidth. The first line of a paragraph inside this environment is indented.

```
317 \newenvironment{quotation}  
318 { \list{}{\setlength\listparindent{1.5em}%  
319 \setlength\itemindent{\listparindent}%  
320 \setlength\rightmargin{\leftmargin}}%  
321 \item[]  
322 \endlist}
```

### 5.5.3 Quote

**quote** The quote environment is like the quotation environment except that paragraphs are not indented.

```
323 \newenvironment{quote}  
324 { \list{}{\setlength\rightmargin{\leftmargin}}%  
325 \item[]  
326 \endlist}
```

### 5.5.4 Theorem

This document class does not define it's own theorem environments, the defaults, supplied by the L<sup>A</sup>T<sub>E</sub>X kernel (ltthm.dtx) are available.

## 5.6 Setting parameters for existing environments

### 5.6.1 Array and tabular

- \arraycolsep The columns in an array environment are separated by  $2\arraycolsep$ .  
327 \setlength{\arraycolsep}{5pt}
- \tabcolsep The columns in an tabular environment are separated by  $2\tabcolsep$ .  
328 \setlength{\tabcolsep}{6pt}
- \arrayrulewidth The width of vertical rules in the array and tabular environments is given by \arrayrulewidth.  
329 \setlength{\arrayrulewidth}{.4pt}
- \doublerulesep The space between adjacent rules in the array and tabular environments is given by \doublerulesep.  
330 \setlength{\doublerulesep}{2pt}

### 5.6.2 Tabbing

- \tabbingsep This controls the space that the \` command puts in. (See L<sup>A</sup>T<sub>E</sub>X manual for an explanation.)  
331 \setlength{\tabbingsep}{\labelsep}

### 5.6.3 Minipage

- \@minipagerestore The macro \@minipagerestore is called upon entry to a minipage environment to set up things that are to be handled differently inside a minipage environment. In the current styles, it does nothing.
- \@mpfootins Minipages have their own footnotes; \skip\@mpfootins plays same rôle for footnotes in a minipage as \skip\footins does for ordinary footnotes.  
332 \skip\@mpfootins = \skip\footins

### 5.6.4 Framed boxes

- \fboxsep The space left by \fbox and \framebox between the box and the text in it.
- \fboxrule The width of the rules in the box made by \fbox and \framebox.  
333 \setlength{\fboxsep}{3pt}  
334 \setlength{\fboxrule}{.4pt}

### 5.6.5 Equation and eqnarray

\theequation The equation counter will be typeset using arabic numbers.  
335 \renewcommand{\theequation}{\@arabic\c@equation}

\jot \jot is the extra space added between lines of an eqnarray environment. The default value is used.  
336 % \setlength{\jot}{3pt}

\eqnnum The macro \eqnnum defines how equation numbers are to appear in equations. Again the default is used.  
337 % \def\eqnnum{(\theequation)}

## 5.7 Font changing

Here we supply the declarative font changing commands that were common in L<sup>A</sup>T<sub>E</sub>X version 2.09 and earlier. These commands work in text mode *and* in math mode. They are provided for compatibility, but one should start using the \text... and \math... commands instead. These commands are redefined using \renewfontswitch, a command with three arguments: the user command to be defined; L<sup>A</sup>T<sub>E</sub>X commands to execute in text mode and L<sup>A</sup>T<sub>E</sub>X commands to execute in math mode.

\rm The commands to change the family.  
\tt 338 \DeclareOldFontCommand{\rm}{\normalfont\rmfamily}{\mathrm}  
\sf 339 \DeclareOldFontCommand{\sf}{\normalfont\sffamily}{\mathsf}  
340 \DeclareOldFontCommand{\tt}{\normalfont\ttfamily}{\mathtt}

\bf The command to change to the bold series. One should use \mdseries to explicitly switch back to medium series.  
341 \DeclareOldFontCommand{\bf}{\normalfont\bfseries}{\mathbf}

\sl And the commands to change the shape of the font. The slanted and small caps \it shapes are not available by default as math alphabets, so those changes do nothing \sc in math mode. One should use \upshape to explicitly change back to the upright shape.  
342 \DeclareOldFontCommand{\it}{\normalfont\itshape}{\mathit}  
343 \DeclareOldFontCommand{\sl}{\normalfont\slshape}{\relax}  
344 \DeclareOldFontCommand{\sc}{\normalfont\scshape}{\relax}

\cal The commands \cal and \mit should only be used in math mode, outside math mode they have no effect. Currently the New Font Selection Scheme defines these commands to generate warning messages. Therefore we have to define them ‘by hand’.  
345 \DeclareRobustCommand\*\{\cal\}{\@fontswitch{\relax}{\mathcal}}  
346 \DeclareRobustCommand\*\{\mit\}{\@fontswitch{\relax}{\mathnormal}}

## 5.8 Footnotes

**\footnoterule** Usually, footnotes are separated from the main body of the text by a small rule. This rule is drawn by the macro `\footnoterule`. We have to make sure that the rule takes no vertical space (see `plain.tex`) so we compensate for the natural height of the rule of 0.4pt by adding the right amount of vertical skip.

To prevent the rule from colliding with the footnote we first add a little negative vertical skip, then we put the rule and make sure we end up at the same point where we began this operation.

```
347 \renewcommand\footnoterule{%
348   \kern-.1p@
349   \hrule \width .4\columnwidth
350   \kern .6\p@}
```

**\c@footnote** A counter for footnotes.

```
351 % \newcounter{footnote}
```

**\@makefntext** The footnote mechanism of L<sup>A</sup>T<sub>E</sub>X calls the macro `\@makefntext` to produce the actual footnote. The macro gets the text of the footnote as its argument and should use `\@makefnmark` to produce the mark of the footnote. The macro `\@makefntext` is called when effectively inside a `\parbox` of width `\columnwidth` (i.e., with `\hsize = \columnwidth`).

An example of what can be achieved is given by the following piece of T<sub>E</sub>X code.

```
\long\def\@makefntext#1{%
  \setpar{\@par
    \tempdima = \hsize
    \advance\tempdima-10pt
    \parshape \one 10pt \tempdima}%
  \par
  \parindent 1em\noindent
  \hb@xt@.z@\hss\@makefnmark}#1}
```

The effect of this definition is that all lines of the footnote are indented by 10pt, while the first line of a new paragraph is indented by 1em. To change these dimensions, just substitute the desired value for ‘10pt’ (in both places) or ‘1em’. The mark is flush right against the footnote.

In this document class we use a simpler macro, in which the footnote text is set like an ordinary text paragraph, with no indentation except on the first line of a paragraph, and the first line of the footnote. Thus, all the macro must do is set `\parindent` to the appropriate value for succeeding paragraphs and put the proper indentation before the mark.

```
352 \long\def\@makefntext#1{%
353   \noindent
354   \hangindent 5\p@
355   \hb@xt@.5\p@{\hss\@makefnmark}#1}
```

`\@makefnmark` The footnote markers that are printed in the text to point to the footnotes should be produced by the macro `\@makefnmark`. We use the default definition for it.

356 %\def\@makefnmark{\hbox{\$^{\scriptscriptstyle \m@th}\!\!\$}{\@thefnmark}}}

## 5.9 Words

`\ccname` This document class is for documents prepared in the English language. To prepare a version for another language, various English words must be replaced. All the `\pagename` English words that require replacement are defined below in command names.

`\headtoname` 357 `\newcommand*{\ccname}{cc}`  
358 `\newcommand*{\enclname}{encl}`  
359 `\newcommand*{\pagename}{Page}`  
360 `\newcommand*{\headtoname}{To}`

## 5.10 Date

`\today` This macro uses the `\month`, `\day` and `\year` to provide the date of the L<sup>A</sup>T<sub>E</sub>X-run.

361 `\newcommand*{\today}{\ifcase\month\or`  
362 `January\or February\or March\or April\or May\or June\or`  
363 `July\or August\or September\or October\or November\or December\fi`  
364 `\space\day, \year}`

## 5.11 Two column mode

`\columnsep` This gives the distance between two columns in two column mode.

365 `\setlength\columnsep{10\p@}`

`\columnseprule` This gives the width of the rule between two columns in two column mode. We have no visible rule.

366 `\setlength\columnseprule{0\p@}`

## 5.12 The page style

We have `plain` pages in this document class by default. We use arabic page numbers.

367 `\pagestyle{plain}`  
368 `\pagenumbering{arabic}`

## 5.13 Single or double sided printing

We don't try to make each page as long as all the others.

369 `\raggedbottom`

\@texttop The document class letter sets \@texttop to \vskip 0pt plus .00006fil on the first page of a letter, which centers a short letter on the page. This fil value may have to be changed for other letterheads. This setting has to be done after \raggedbottom is executed, since the latter sets \@texttop to \relax.

```
370 \def\@texttop{\ifnum\c@page=1\vskip \z@ plus.00006fil\relax\fi}
```

We always start in one column mode.

```
371 \onecolumn  
372 </letter>
```

## Index

Numbers written in italic refer to the page where the corresponding entry is described, the ones underlined to the code line of the definition, the rest to the code lines where the entry is used.

Symbols		A
\@par	141, 160, 175	\@minipagerestore . <u>332</u>
\auxout	146	\@mlabel .. 127, 147, <u>249</u>
\begin{parpenalty}	<u>261</u>	\@mparswitchfalse . 34
\bsphack	169	\@mparswitchtrue .. 32
\colht	230	\@mpfootins .. <u>332</u>
\colroom	230	\@nobreakcr ... 161, 171
\date	85, 92, 183, 188	\@nobreakvspace 162, 163
\eha	30	\@nobreakvspace ..
\endparpenalty	<u>261</u>	..... 164, 165
\eqnnum	<u>337</u>	\@normalcr ... 171, 173
\esphack	169	\@oddfoot .. <u>81</u> ,
\evenfoot	<u>81</u> , 83, 97, 113	83, 90, 96, 100, 112
\evenhead	<u>81</u> , 87, 97	\@oddhead ... <u>81</u> , 84,
\fontswitch	345, 346	87, 91, 96, 99, 111
\gobbletwo	249	\@onlypreamble ... 132
\hangfrom	211, 216	\@processsto ... 140, <u>150</u>
\highpenalty	<u>47</u>	\@ptsize .. <u>1</u> ,
\ifstar	164, 171	25–27, 41, 102, 233
\itempenalty	<u>261</u>	\@roman .. 289
\latexerr	29	\@startlabels ..
\listI	<u>264</u>	... 126, 129, <u>245</u>
\listi	<u>264</u>	\@tempdima 22, 24, 69–72
\listii	<u>270</u>	\@texttop ... 224, <u>370</u>
\listiii	<u>270</u>	\@thefnmark .. 356
\listiv	<u>270</u>	\@twosidefalse ... 34
\listv	<u>270</u>	\@twosidetrue ... 32
\listvi	<u>270</u>	\@unexpandable@protect
\lowpenalty	<u>47</u> , 261–263	... 145
\mainaux	129, 131	\@width .. 349
\makefnmark	355, <u>356</u>	\@xproc .. <u>150</u>
\makefntext	<u>352</u>	\@yproc .. <u>150</u>

  

	B
\baselineskip	..... 240
\baselinestretch	.. <u>44</u>
\bf	..... <u>341</u>
\bigskipamount	.... <u>205</u>
\boxmaxdepth	..... 242
\brokenpenalty	.... <u>56</u>

  

	C
\c@enumi	..... 287
\c@enumii	..... 288
\c@enumiii	..... 289
\c@enumiv	..... 290
\c@equation	..... 335
\c@footnote	..... <u>351</u>
\c@page	... 135, 138, 370
\cal	..... <u>345</u>
\cc	..... <u>208</u>
\ccname	..... 211, <u>357</u>
\clearpage	..... 131
\closing	..... <u>194</u>
\clubpenalty	.... <u>50</u>
\columnsep	... 232, <u>365</u>
\columnseprule	.... <u>366</u>

\columnwidth	349	\if@files	128, 131, 142	\leftmarginv	..... ..... 250, 281, 282
D		\if@twoside	81, 135	\leftmarginvi	..... ..... 250, 284, 285
\DeclareOldFontCommand	..... 338–344	\ifodd	135	letter (environment)	133
\DeclareRobustCommand	.... 163, 345, 346	\ignorespaces	..... 84, 91, 140, 186, 200, 212, 217, 247	\lineskip	..... 42, 241
description (environment)	..... 302	\immediate	129, 131, 146	\listparindent	..... 312, 318, 319
\descriptionlabel	..... 304, 306	\indentedwidth	178, 199	\location	..... 114, 122
\displaywidowpenalty	52	\interlinepenalty	..... 55, 139, 159, 174	\longindentation	..... 176, 180, 198
\doublerulesep	330	\it	..... 342	M	
E		\item	315, 321, 325	\makelabel	..... 304
\encl	208	\itemindent	..... 303, 311, 312, 319	\makelabels	..... 124
\enclname	216, 357	\itemsep	267, 277, 310	\marginparpush	..... 76
environments:		\itshape	..... 342	\marginparsep	..... 76
description	17	J		\marginparwidth	.... 64
letter	10	\jot	..... 336	\mathbf	..... 341
quotation	18	L		\mathcal	..... 345
quote	18	\labelcount	.... 221, 222	\mathit	..... 342
verse	18	\labelenumi	..... 291	\mathnormal	..... 346
\evensidemargin	64, 228	\labelenumii	..... 291	\mathrm	..... 338
F		\labelenumiii	..... 291	\mathsf	..... 339
\fboxrule	333	\labelenumiv	..... 291	\mathtt	..... 340
\fboxsep	333	\labelitemi	..... 298	\medskipamount	.... 205
\footins	80, 332	\labelitemii	..... 298	\medskipamount	200, 206
\footnoterule	347	\labelitemiii	..... 298	\mit	..... 345
\footnotesep	79	\labelitemiv	..... 298	\mlabel	..... 127, 246
\footnotesize	107, 238	\labelsep	.... 257, 272, 275, 280, 283, 286, 306, 331	N	
\footskip	59	\labelwidth	.... 257, 271, 272, 274, 275, 279, 280, 282, 283, 285, 286, 303	\name	..... 114, 119
\fromaddress	116, 119, 181, 187, 197	\leftmargin	.... 250, 264, 270, 273, 278, 281, 284, 303, 313, 314, 320, 324	\newcount	..... 221
\fromlocation	.... 109, 117, 119	\leftmargini	.... 250, 258, 264	\nobreakcr	..... 163
\fromname	114, 119, 202	\leftmarginii	.... 250, 270, 271	\nobreakvspace	..... 163
\fromsig	.... 115, 119, 201, 203	\leftmarginiii	.... 250, 273, 274	\nobreakvspace	.... 163
H		\leftmarginiv	.... 250, 278, 279	normalfont	... 112, 113, 211, 216, 299, 307, 338–344
\hb@xt@	101, 355	O		\normallineskip	.... 42
\headheight	57	\oddsidemargin	.... 64, 227		
\headsep	57, 226	\onecolumn	..... 371		
\headtoname	84, 91, 357	\opening	..... 181		
I		\overfullrule	.... 35, 36		
\if@compatibility	.... 28, 60, 64	P			
		\p@enumii	..... 295		

\p@enumiii .....	<u>295</u>	\returnaddress .....	<u>147</u> , <u>220</u>	\textwidth .....
\p@enumiv .....	<u>295</u>	\rm .....	<u>338</u>	60, 71, 101, 177,
\pagebreak .....	<u>141</u>			179, 210, 215, 231
\pagename ..	<u>86</u> , <u>93</u> , <u>357</u>	<b>S</b>		\theenumi .....
\pagenumbering .....	<u>368</u>	\sc .....	<u>342</u>	. <u>287</u> , 291, 295, 296
\paperheight 4, 7, 10,		\scshape .....	<u>344</u>	\theenumii <u>287</u> , 292, 296
13, 16, 19, 22, 23		\sf .....	<u>338</u>	\theenumiii <u>287</u> , 293, 297
\paperwidth .....		\sffamily .....	<u>339</u>	\theenumiv ... <u>287</u> , 294
.. 5, 8, 11, 14,		\signature ... <u>114</u> , <u>120</u>		\theequation ... <u>335</u> , 337
17, 20, 23, 24, 69		\sl .....	<u>342</u>	\thepage <u>86</u> , <u>93</u> , <u>112</u> , <u>113</u>
\parbox 199, 210, 215, 247		\small .....	<u>105</u> , <u>236</u>	\thispagestyle .....
\parindent ... <u>45</u> , <u>243</u>		\smallskipamount ... <u>205</u>		136, 182, 185
\parsep .....	<u>265</u>	\startbreaks ... <u>172</u> , <u>218</u>		\toaddress ... <u>147</u> ,
\parskip <u>45</u> , <u>187</u> , <u>190</u> ,		\startlabels ... <u>126</u> , <u>222</u>		152, 156, 157, 191
192, 194, 205–207		\stopbreaks ... <u>158</u> , <u>195</u>		\today ... <u>361</u>
\partopsep ... <u>260</u>		\stopletter ... <u>141</u> , <u>219</u>		\toname .....
\postdisplaypenalty ... <u>52</u>		\string ... <u>129</u> , <u>131</u> , <u>147</u>		84, 91, 147, 156, 191
\predisplaypenalty ... <u>52</u>		\strut ... <u>203</u> , <u>212</u> , <u>217</u> , <u>247</u>		\topmargin ... <u>78</u> , <u>225</u>
\ps ... ... <u>208</u>				\topsep ... <u>266</u> , <u>276</u> , <u>277</u>
\ps@empty ... <u>95</u>		<b>T</b>		\tt ... <u>338</u>
\ps@firstpage ... <u>98</u>		\tabbingsep ... <u>331</u>		\ttfamily ... <u>340</u>
\ps@headings ... <u>81</u>		\tabcolsep ... <u>328</u>		\twocolumn ... <u>244</u>
\ps@plain ... <u>110</u>		\telephone ... <u>114</u> , <u>123</u>		
		\telephonenum ...		<b>V</b>
<b>Q</b>				
quotation (environment) ...	<u>317</u>			
quote (environment) ...	<u>323</u>	\textasteriskcentered		\vadjust ... <u>169</u>
		.....		\verse (environment) ... <u>308</u>
		300		\vsizer ... <u>230</u>
		\textbullet		
		298		
				<b>W</b>
<b>R</b>		\textendash		
\raggedleft ... <u>183</u> , <u>186</u>		\textheight ... <u>62</u> , <u>229</u> , <u>230</u>		\widowpenalty ... <u>50</u>
\raisebox ... <u>100</u>		\textperiodcentered	<u>301</u>	\write ... <u>129</u> , <u>131</u> , <u>146</u>

## Change History

v1.0		\sf: Added compatibility mode support.	.....	<u>20</u>
General: Use class ltxdoc document class	.....	1	v1.1	
v1.0a		General: Changes to make it work with compatibility mode.	.....	<u>1</u>
General: Corrected typo, A4 is not 279 mm high	.....	Corrected typo in \renewcommand, doubled hash marks.	.....	<u>4</u>
\bf: Added compatibility mode support.	.....	\bf: Changed \@newfontswitch to \crenewfontswitch, removed switch.	.....	<u>20</u>
\cal: Macro added	.....	\sc: Changed \@newfontswitch to \crenewfontswitch, removed switch.	.....	<u>20</u>
\mit: Macro added	.....			
\sc: Added compatibility mode support.	.....			

\sf: Changed \newfontswitch to \renewfontswitch, removed switch.	20	insertion of a blank page when necessary.	10
v1.1a General: Removed float parms	1	\ps@empty: Also make even feet and head empty	8
v1.1b \sc: Added forgotten re.	20	\ps@headings: Added twoside support	8
v1.1c General: Moved definition of \texttop to initialization section, to counteract setting of \texttop in \raggedbottom.	1	\ps@plain: Added definition of \evenfoot because of twoside option	9
v1.1d General: Corrected margins: Now computed from \paperwidth and \textwidth, so that the text is horizontally centered.	1	\typeout: Removed message	1
\marginparwidth: Corrected margins: Now computed from \paperwidth and \textwidth.	6	Use LaTeX instead of LaTeX2e in messages	1
v1.1e General: Corrected checksum	1	v1.2g General: Removed the use of \fileversion c.s.	1
v1.2a General: Changed label producing commands in .aux file.	1	\labelitemii: Inserted \normalfont	17
Removed onecolumn and twocolumn options.	1	\ps@headings: Made running heads the same on odd and even pages	8
v1.2b General: Moved driver further up.	1	v1.2j General: Corrected driver code.	1
v1.2c \makefntext: Always call \makefnmark.	21	v1.2k General: Various documentation enhancements	1
General: Always write .aux file.	1	\ps@headings: Added a missing brace	8
v1.2d \sf: \renewfontswitch has become \DeclareOldFontCommand	20	v1.2m \telephone: Removed typo (#[] instead of [1])	9
General: Added execution of ‘one-side’ option	4	v1.2n General: Setting of \maxdepth and \@maxdepth already happens in the size.. files, removed here	6
Added oneside option and two-side option in native mode	3	\labelitemiv: renamed \labelitemiii to \labelitemii	17
\letter: When printing twosided a new letter shouldn’t start on the back of the previous one. Added		\marginparwidth: Added fixed values for these parameters in compatibility mode	6
		\textheight: Setting \textheight to a fixed value should only happen in compatibility mode	6
		\textwidth: Setting \textwidth to a fixed value should only happen in compatibility mode	6

v1.2o		\startlabels: changed value of \columnsep by 1pt . . . . .	14
General: Added the option land- scape . . . . .	3		
v1.2p		General: removed a superfluous brace . . . . .	1
General: Use \newcommand* to de- fine user-level commands that take an argument . . . . .	1		
letter: No longer redefine \protect but use one of the available settings . . . . .	10		
\mit: Now define \cal and \mit us- ing \DeclareRobustCommand* . . . .	20		
\mlabel: Redefined \mlabel to not use the \setbox primitive . . .	15		
v1.2q		\labelitemii: replaced -- with \textradash . . . . .	17
General: cleaned up \changes entries . . . . .	1		
replaced \hbox to by \hbox@xt@ .	1		
\descriptionlabel: made com- mand short . . . . .	18		
\mlabel: changed width of the la- bels slightly to prevent L <sup>T</sup> E <sub>X</sub> stuffing two on each line . . .	15		
v1.2r		\ps: replace \reset@font with \normalfont; remove \rm . . . . .	13
\ps@plain: replace \rmfamily with \normalfont (PR 1578) . . . . .	9		
v1.2s		\nobreakvspace: Made robust pr/2049 . . . . .	11
v1.2t		\labelitemiv: Changed to \textrbullet, \textasteriskcentered and \textperiodcentered . . .	17
v1.2u			
v1.2w		\nobreakcr: Simplify definition, for ltspace 1.2u. /2341 . . . . .	11
v1.2x			